

ANALOG WAY MIDRA™ 4K

Module: IMAGESLIBRARY

Crestron 3-series & 4-series

Date: **February 12, 2021**
Driver version: **V1.0.0**
Compatible with: **Midra™ 4K Firmware v1.1.9 or above**

GENERAL

This module provides information about the image library of the Midra™ 4K video processor.

CONTROL

General

AW_ImgLib_RefreshInfos	Digital_in	Pulse this signal to force the download and processing of information from the Midra 4K video processor. Most of the time, this signal is never used
------------------------	------------	--

Status

AW_ImgLib_Valid_FB[X]	Digital_out	Equals 1 when the image X of the library is valid, 0 otherwise
AW_ImgLib_Used_FB[X]	Digital_out	Equals 1 when the image X of the library is associated to one or more screen image slots (background and/or foreground), 0 otherwise

Format

AW_ImgLib_Format_FB[X]	String_Out	The resolution of the image X in the library (syntax: width x Height in pixels)
------------------------	------------	---

FileName

AW_ImgLib_FileName_FB[X]	String_Out	The filename of the image X in the library
--------------------------	------------	--