

Midra™ 4K Series supports both IPv4 and IPv6. This document summarizes all information needed for network administration

IPv4 configuration

Addressing modes	Static / DHCP	
Default addressing mode	Static	
Default IP address	192.168.2.140	
Default Net Mask	255.255.255.0	
Gateway	None	
Opened ports	53	Domain Name Service (DNS) port Opened only if DHCP finds a DNS server
	80	Hypertext Transfer Protocol (HTTP) port For Web RCS and REST API
	10500	Analog Way proprietary port 1
	10506	Analog Way proprietary port 2
	10606	Analog Way JSON (AWJ) protocol port For external controllers
	10691	ControlBox JSON(CBJ) protocol port For RC400T
	15465	Secure Shell (SSH) port protected by a RSA key. No possible password

IPv6 configuration

Default IPv6 state	Disabled	
Addressing modes	Static or DHCP	
Default addressing mode	Static	
Default IP address	None	
Default Net Mask	FFFF:FFFF:FFFF:FFFF:0000:0000:0000:0000	
Gateway	None	
Opened ports	53	Domain Name Service (DNS) port Opened only if DHCP finds a DNS server
	80	Hypertext Transfer Protocol (HTTP) port. For WebRCS and REST API
	10500	Analog Way Proprietary port 1
	10606	Analog Way JSON (AWJ) protocol port For external controllers
	10691	Control Box JSON(CBJ) protocol port For RC400T
	15465	Secure Shell (SSH) port with RSA key encryption. No possible password